

QRSTUFF.COM

BATCH PROCESSING GUIDE

QRStuff.com offers a batch processing feature that enables users to generate dozens, hundreds or even thousands of QR codes all at once, streamlining tasks such as inventory management, event ticketing, and bulk printing. Here's a step-by-step guide to the process.

CREATING A BATCH UPLOAD QR CODE

- Select the desired data type on [QRStuff's QR Code generator](#).

1. DATA TYPE 2. DESTINATION 3. STYLE 4. SETUP

Dynamic QR Codes
Track performance and make updates anytime

Search Type...

URL Plain Text Email Phone SMS

WiFi Login Snapchat UPI Form App

- Now on the next step, click on “Bulk Create” to create QR Codes in bulk for the data type you selected

1. DATA TYPE 2. DESTINATION 3. STYLE 4. SETUP

< Data Type

Text

Bulk Create ⓘ

Style Your QR Code >

- You can also change the data type OR select multiple data types simultaneously for the bulk process, from the dropdown menu that appears when you click on the name of the data type you selected.

To download a sample data file, click the link to get an Excel (.xlsx) file for the selected data type(s).

1. DATA TYPE 2. DESTINATION 3. STYLE 4. SETUP

< Data Type

Select Data Types

Plain Text x Dropbox x Event x

- App Download
- Bitcoin
- Contact Details
- Digital Business Card
- Discord
- Email Address
- Email Message
- Eventbrite
- Facebook
- Facebook Like
- Google Form
- Google Review

- Now open the sample file(s) and fill the columns with the help of the instructions and enter only one of the inputs from the listed allowed inputs in each column.
Crucial Note: The sheet name(s) in your file must always be exactly the same as the data type name(s) (e.g., TEXT, BITCOIN, DROPBOX).

	A	B	C	D	E	F	G	H	I	J	K	L	M	N	O	P	Q	
1	text	name	dynamic	format	size	r_correction_l	gradient	color.bg	color.fg	color.finder	color.finder_eyor	alignment_inr	alignment_o	color.gradient	color.center	color.transparent	module_shape	finder
2	Test text	QR-01	TRUE	pdf	128 L		radial	#####	#000000	#000000	#000000	#000000	#000000	#000000	#000000	TRUE	square	square
3				svg	256 M		vertical										round	round
4				png	512 Q		horizontal										dot	circle
5				jpg	1024 H		diagonal										square_outlined	square_outlined
6				eps			inverse_diagonal										square_rounded_corners	square_rounded_corners
7				dxf													dots_connected	dots_connected
8																		
9																		
10																		
11																		
12																		
13																		
14																		
15																		
16																		
17																		
18																		
19																		
20																		
21																		
22																		
23																		
24																		
25	INSTRUCTIONS:																	
26	Dynamic column, if left blank will create a static QR Code																	
27	Please remove these instructions before uploading this file for batch processing																	
28																		
29																		

- Enter the name of the batch of QR Codes that will be generated and the project it should appear in.

1. DATA TYPE

2. DESTINATION

3. STYLE

4. SETUP

< Setup

Your batch is ready to process

You can still go back to modify your batch.

* Batch Name

Name to be shown in dashboard.

* Select Project

Non - default project

x v

Organize QR codes in projects.

☐ Use higher error correction i



Submit




- Click on submit and within a few minutes, the batch of QR Codes will appear under the desired project on the dashboard and will be sent to your registered email ID in a zip file.

PREPARING YOUR EXCEL FILE

For Discord, Dropbox, Email Address, Eventbrite, Google Form, Instagram, iTunes, LinkedIn, Newsletter, Phone Number, Plain Text, Snapchat, Spotify, Telegram, TikTok, Vimeo, Website URLs, X (Twitter), Zoom.

COLUMN A: Type the URL or text related to the above data types.

COLUMN B: Enter the name of each individual QR Code in the batch.

COLUMN C: For dynamic QR Codes, enter true, and leave blank for a static QR Code.

COLUMN D: Enter the format of the QR Code.

COLUMN E: Specify the size of the QR Code.

COLUMN F: Choose the error correction level.

COLUMN G: Select the style of Gradient, or leave blank if you do not wish to apply gradient.

COLUMN H: Enter the background color for the QR Code.

COLUMN I: Enter the foreground color for the QR Code.

COLUMN J: Enter the finder color for the QR Code.

COLUMN K: Enter the finder eye color for the QR Code.

COLUMN L: Enter the inner alignment color for the QR Code.

COLUMN M: Enter the outer alignment color for the QR Code.

COLUMN N: Enter the color of the gradient.

COLUMN O: Enter the color of the center text.

COLUMN P: Enter the transparency of the background as true or false

COLUMN Q: Select the module shape from the available ones.

COLUMN R: Select the finder shape from the available ones.

COLUMN S: Select the finder eye shape from the available ones.

COLUMN T: Select the outer alignment shape from the available ones.

COLUMN U: Select the inner alignment shape from the available ones.

COLUMN V: Enter the text you want in the center.

For App Download:

COLUMN A-I: Enter the iTunes/iTunes for iPad/Google Play for Tablet/Google Play/Blackberry Legacy/Blackberry 10/ Microsoft Store URL in one of the columns

COLUMN J: Enter the Fallback URL (the URL to which the QR Code will redirect to if the first URL doesn't work)

COLUMN K: Enter the name of each individual QR Code in the batch.

COLUMN L: For dynamic QR Codes, enter true, and leave blank for a static QR Code.

COLUMN M: Enter the format of the QR Code.

COLUMN N: Specify the size of the QR Code.

COLUMN O: Choose the error correction level.

COLUMN P: Select the style of Gradient, or leave blank if you do not wish to apply gradient.

COLUMN Q: Enter the background color for the QR Code.

COLUMN R: Enter the foreground color for the QR Code.

COLUMN S: Enter the finder color for the QR Code.

COLUMN T: Enter the finder eye color for the QR Code.
COLUMN U: Enter the inner alignment color for the QR Code.
COLUMN V: Enter the outer alignment color for the QR Code.
COLUMN W: Enter the color of the gradient.
COLUMN X: Enter the color of the center text.
COLUMN Y: Enter the transparency of the background as true or false.
COLUMN Z: Select the module shape from the available ones.
COLUMN AA: Select the finder shape from the available ones.
COLUMN AB: Select the finder eye shape from the available ones.
COLUMN AC: Select the outer alignment shape from the available ones.
COLUMN AD: Select the inner alignment shape from the available ones.
COLUMN AE: Enter the text you want in the center.

For Bitcoin:

COLUMN A: Enter the address of your Bitcoin wallet.
COLUMN B: Set the desired amount.
COLUMN C: Enter the label for each transaction.
COLUMN D: Add a descriptive message for each transaction.
COLUMN E: Enter the name of each individual QR Code in the batch.
COLUMN F: For dynamic QR Codes, enter true, and leave blank for a static QR Code.
COLUMN G: Enter the format of the QR Code.
COLUMN H: Specify the size of the QR Code.
COLUMN I: Choose the error correction level.
COLUMN J: Select the style of Gradient, or leave blank if you do not wish to apply gradient.
COLUMN K: Enter the background color for the QR Code.
COLUMN L: Enter the foreground color for the QR Code.
COLUMN M: Enter the finder color for the QR Code.
COLUMN N: Enter the finder eye color for the QR Code.
COLUMN O: Enter the inner alignment color for the QR Code.
COLUMN P: Enter the outer alignment color for the QR Code.
COLUMN Q: Enter the color of the gradient.
COLUMN R: Enter the color of the center text.
COLUMN S: Enter the transparency of the background as true or false.
COLUMN T: Select the module shape from the available ones.
COLUMN U: Select the finder shape from the available ones.
COLUMN V: Select the finder eye shape from the available ones.
COLUMN W: Select the outer alignment shape from the available ones.
COLUMN X: Select the inner alignment shape from the available ones.
COLUMN Y: Enter the text you want in the center.

For Contact Details:

COLUMN A: Enter the first name.
COLUMN B: Enter the last name.
COLUMN C: Add the title (designation).

COLUMN D: Enter any additional names.
COLUMN E: Enter Prefix for the name, e.g., Mr, Mrs, Ms, etc.
COLUMN F: Enter Suffix for the name, e.g., Junior, II, etc.
COLUMN G: Enter the telephone number.
COLUMN H: Enter the cell phone number.
COLUMN I: Enter the fax number.
COLUMN J: Enter the email address.
COLUMN K: Enter the name of the organisation.
COLUMN L: Enter the street address.
COLUMN M: Enter the city.
COLUMN N: Enter the state.
COLUMN O: Mention the pincode of the area.
COLUMN P: Enter the name of the country.
COLUMN Q: Enter the URL to the website.
COLUMN R: Enter any additional notes.
COLUMN S: Select the type of the card, either mecard or vcard
COLUMN T: Enter the name of each individual QR Code in the batch.
COLUMN U: For dynamic QR Codes, enter true, and leave blank for a static QR Code.
COLUMN V: Enter the format of the QR Code.
COLUMN W: Specify the size of the QR Code.
COLUMN X: Choose the error correction level.
COLUMN Y: Select the style of Gradient, or leave blank if you do not wish to apply gradient.
COLUMN Z: Enter the background color for the QR Code.
COLUMN AA: Enter the foreground color for the QR Code.
COLUMN AB: Enter the finder color for the QR Code.
COLUMN AC: Enter the finder eye color for the QR Code.
COLUMN AD: Enter the inner alignment color for the QR Code.
COLUMN AE: Enter the outer alignment color for the QR Code.
COLUMN AF: Enter the color of the gradient.
COLUMN AG: Enter the color of the center text.
COLUMN AH: Enter the transparency of the background as true or false.
COLUMN AI: Select the module shape from the available ones.
COLUMN AJ: Select the finder shape from the available ones.
COLUMN AK: Select the finder eye shape from the available ones.
COLUMN AL: Select the outer alignment shape from the available ones.
COLUMN AM: Select the inner alignment shape from the available ones.
COLUMN AN: Enter the text you want in the center.

For Digital Business Card:

COLUMN A: Enter the first name of the contact.
COLUMN B: Enter the last name of the contact.
COLUMN C: Add the title of the contact.
COLUMN D: Enter the name prefix, e.g., Mr, Mrs, Ms, etc.
COLUMN E: Enter the name suffix, e.g., Junior, II, etc.

COLUMN F: Enter the telephone number of the contact.
COLUMN G: Enter the cell phone number of the contact.
COLUMN H: Enter the fax number of the contact.
COLUMN I: Enter the email address of the contact.
COLUMN J: Enter the organization name of the contact.
COLUMN K: Enter the street address of the contact.
COLUMN L: Enter the city of the contact.
COLUMN M: Enter the state of the contact.
COLUMN N: Enter the postcode of the contact.
COLUMN O: Enter the country of the contact.
COLUMN P: Enter the URL associated with the contact.
COLUMN Q: Enter any additional notes about the contact.
COLUMN R: Enter the QR code name or title.
COLUMN S: For dynamic QR Codes, enter true, and leave blank for a static QR Code.
COLUMN T: Enter the format of the QR Code.
COLUMN U: Choose the error correction level.
COLUMN V: Specify the size of the QR Code.
COLUMN W: Enter the DPI (resolution) for the QR Code.
COLUMN X: Select the style of Gradient, or leave blank if you do not wish to apply gradient.
COLUMN Y: Enter the background color for the QR Code.
COLUMN Z: Enter the foreground color for the QR Code.
COLUMN AA: Enter the finder color for the QR Code.
COLUMN AB: Enter the finder eye color for the QR Code.
COLUMN AC: Enter the inner alignment color for the QR Code.
COLUMN AD: Enter the outer alignment color for the QR Code.
COLUMN AE: Enter the color of the gradient.
COLUMN AF: Enter the color of the center text.
COLUMN AG: Enter the transparency of the background as true or false.
COLUMN AH: Select the module shape from the available ones.
COLUMN AI: Select the finder shape from the available ones.
COLUMN AJ: Select the finder eye shape from the available ones.
COLUMN AK: Select the outer alignment shape from the available ones.
COLUMN AL: Select the inner alignment shape from the available ones.
COLUMN AM: Enter the text you want in the center.

For Email Message:

COLUMN A: Enter the body of the email.
COLUMN B: Enter the subject of the email.
COLUMN C: Enter the main email address to which the email will be sent.
COLUMN D: Enter the CC email addresses separated by spaces.
COLUMN E: Enter the BCC email addresses separated by spaces.
COLUMN F: Enter the name of each individual QR Code in the batch.
COLUMN G: For dynamic QR Codes, enter true, and leave blank for a static QR Code.

COLUMN H: Enter the format of the QR Code.
COLUMN I: Specify the size of the QR Code.
COLUMN J: Choose the error correction level.
COLUMN K: Select the style of Gradient, or leave blank if you do not wish to apply gradient.
COLUMN L: Enter the background color for the QR Code.
COLUMN M: Enter the foreground color for the QR Code.
COLUMN N: Enter the finder color for the QR Code.
COLUMN O: Enter the finder eye color for the QR Code.
COLUMN P: Enter the inner alignment color for the QR Code.
COLUMN Q: Enter the outer alignment color for the QR Code.
COLUMN R: Enter the color of the gradient.
COLUMN S: Enter the color of the center text.
COLUMN T: Enter the transparency of the background as true or false.
COLUMN U: Select the module shape from the available ones.
COLUMN V: Select the finder shape from the available ones.
COLUMN W: Select the finder eye shape from the available ones.
COLUMN X: Select the outer alignment shape from the available ones.
COLUMN Y: Select the inner alignment shape from the available ones.
COLUMN Z: Enter the text you want in the center.

For Event:

COLUMN A: Enter the name of the event.
COLUMN B: Enter the starting date and time in the format of
YYYY-MM-DDTHH:MM:SS+HH:MM
COLUMN C: Enter the ending date and time in the format of
YYYY-MM-DDTHH:MM:SS+HH:MM
COLUMN D: Enter the location of the event.
COLUMN E: Enter the exact address of the event.
COLUMN F: Enter the longitude value of the location of the event.
COLUMN G: Enter the latitude value of the location of the event.
COLUMN H: Enter the name of each individual QR Code in the batch.
COLUMN I: For dynamic QR Codes, enter true, and leave blank for a static QR Code.
COLUMN J: Enter the format of the QR Code.
COLUMN K: Specify the size of the QR Code.
COLUMN L: Choose the error correction level.
COLUMN M: Select the style of Gradient, or leave blank if you do not wish to apply gradient.
COLUMN N: Enter the background color for the QR Code.
COLUMN O: Enter the foreground color for the QR Code.
COLUMN P: Enter the finder color for the QR Code.
COLUMN Q: Enter the finder eye color for the QR Code.
COLUMN R: Enter the inner alignment color for the QR Code.
COLUMN S: Enter the outer alignment color for the QR Code.
COLUMN T: Enter the color of the gradient.
COLUMN U: Enter the color of the center text.

COLUMN V: Enter the transparency of the background as true or false.
COLUMN W: Select the module shape from the available ones.
COLUMN X: Select the finder shape from the available ones.
COLUMN Y: Select the finder eye shape from the available ones.
COLUMN Z: Select the outer alignment shape from the available ones.
COLUMN AA: Select the inner alignment shape from the available ones.
COLUMN AB: Enter the text you want in the center.

For Facebook:

COLUMN A: Type the ID of your Facebook page.
COLUMN B: Enter the name of each individual QR Code in the batch.
COLUMN C: For dynamic QR Codes, enter true, and leave blank for a static QR Code.
COLUMN D: Enter the format of the QR Code.
COLUMN E: Specify the size of the QR Code.
COLUMN F: Choose the error correction level.
COLUMN G: Select the style of Gradient, or leave blank if you do not wish to apply gradient.
COLUMN H: Enter the background color for the QR Code.
COLUMN I: Enter the foreground color for the QR Code.
COLUMN J: Enter the finder color for the QR Code.
COLUMN K: Enter the finder eye color for the QR Code.
COLUMN L: Enter the inner alignment color for the QR Code.
COLUMN M: Enter the outer alignment color for the QR Code.
COLUMN N: Enter the color of the gradient.
COLUMN O: Enter the color of the center text.
COLUMN P: Enter the transparency of the background as true or false
COLUMN Q: Select the module shape from the available ones.
COLUMN R: Select the finder shape from the available ones.
COLUMN S: Select the finder eye shape from the available ones.
COLUMN T: Select the outer alignment shape from the available ones.
COLUMN U: Select the inner alignment shape from the available ones.
COLUMN V: Enter the text you want in the center.

Note: To find your Facebook ID: refer to <https://www.facebook.com/help/1503421039731588/>

Google Review:

COLUMN A: Enter the Place ID of which you want the review for.
COLUMN B: Enter the place name.
COLUMN C: Enter the place address.
COLUMN D: Enter the name of each individual QR Code in the batch.
COLUMN E: For dynamic QR Codes, enter true, and leave blank for a static QR Code.
COLUMN F: Enter the format of the QR Code.
COLUMN G: Specify the size of the QR Code.
COLUMN H: Choose the error correction level.
COLUMN I: Select the style of Gradient, or leave blank if you do not wish to apply gradient.

COLUMN J: Enter the background color for the QR Code.
COLUMN K: Enter the foreground color for the QR Code.
COLUMN L: Enter the finder color for the QR Code.
COLUMN M: Enter the finder eye color for the QR Code.
COLUMN N: Enter the inner alignment color for the QR Code.
COLUMN O: Enter the outer alignment color for the QR Code.
COLUMN P: Enter the color of the gradient.
COLUMN Q: Enter the color of the center text.
COLUMN R: Enter the transparency of the background as true or false
COLUMN S: Select the module shape from the available ones.
COLUMN T: Select the finder shape from the available ones.
COLUMN U: Select the finder eye shape from the available ones.
COLUMN V: Select the outer alignment shape from the available ones.
COLUMN W: Select the inner alignment shape from the available ones.
COLUMN X: Enter the text you want in the center.

Note: To find your place ID, refer to

<https://developers.google.com/maps/documentation/javascript/examples/places-placeid-finder>

For Location:

COLUMN A: Enter the latitude value of the location if you selected “latlng” as mode.
COLUMN B: Enter the longitude value of the location if you selected “latlng” as mode.
COLUMN C: Enter the address of the location if you selected “address” as mode.
COLUMN D: Enter one of the modes from “latlng” and “address”.
COLUMN E: Enter the name of each individual QR Code in the batch.
COLUMN F: For dynamic QR Codes, enter true, and leave blank for a static QR Code.
COLUMN G: Enter the format of the QR Code.
COLUMN H: Specify the size of the QR Code.
COLUMN I: Choose the error correction level.
COLUMN J: Select the style of Gradient, or leave blank if you do not wish to apply gradient.
COLUMN K: Enter the background color for the QR Code.
COLUMN L: Enter the foreground color for the QR Code.
COLUMN M: Enter the finder color for the QR Code.
COLUMN N: Enter the finder eye color for the QR Code.
COLUMN O: Enter the inner alignment color for the QR Code.
COLUMN P: Enter the outer alignment color for the QR Code.
COLUMN Q: Enter the color of the gradient.
COLUMN R: Enter the color of the center text.
COLUMN S: Enter the transparency of the background as true or false
COLUMN T: Select the module shape from the available ones.
COLUMN U: Select the finder shape from the available ones.
COLUMN V: Select the finder eye shape from the available ones.
COLUMN W: Select the outer alignment shape from the available ones.
COLUMN X: Select the inner alignment shape from the available ones.
COLUMN Y: Enter the text you want in the center.

For PayPal:

COLUMN A: Enter the email of the recipient.
COLUMN B: Enter the item description.
COLUMN C: Enter item product code.
COLUMN D: Enter the item value.
COLUMN E: Enter the currency code.
COLUMN F: Enter the name of each individual QR Code in the batch.
COLUMN G: For dynamic QR Codes, enter true, and leave blank for a static QR Code.
COLUMN H: Enter the format of the QR Code.
COLUMN I: Specify the size of the QR Code.
COLUMN J: Choose the error correction level.
COLUMN K: Select the style of Gradient, or leave blank if you do not wish to apply gradient.
COLUMN L: Enter the background color for the QR Code.
COLUMN M: Enter the foreground color for the QR Code.
COLUMN N: Enter the finder color for the QR Code.
COLUMN O: Enter the finder eye color for the QR Code.
COLUMN P: Enter the inner alignment color for the QR Code.
COLUMN Q: Enter the outer alignment color for the QR Code.
COLUMN R: Enter the color of the gradient.
COLUMN S: Enter the color of the center text.
COLUMN T: Enter the transparency of the background as true or false.
COLUMN U: Select the module shape from the available ones.
COLUMN V: Select the finder shape from the available ones.
COLUMN W: Select the finder eye shape from the available ones.
COLUMN X: Select the outer alignment shape from the available ones.
COLUMN Y: Select the inner alignment shape from the available ones.
COLUMN Z: Enter the text you want in the center.

For SMS Message:

COLUMN A: Enter the phone number of the recipient of the message.
COLUMN B: Enter the message.
COLUMN C: Enter the name of each individual QR Code in the batch.
COLUMN D: For dynamic QR Codes, enter true, and leave blank for a static QR Code.
COLUMN E: Enter the format of the QR Code.
COLUMN F: Specify the size of the QR Code.
COLUMN G: Choose the error correction level.
COLUMN H: Select the style of Gradient, or leave blank if you do not wish to apply gradient.
COLUMN I: Enter the background color for the QR Code.
COLUMN J: Enter the foreground color for the QR Code.
COLUMN K: Enter the finder color for the QR Code.
COLUMN L: Enter the finder eye color for the QR Code.
COLUMN M: Enter the inner alignment color for the QR Code.

COLUMN N: Enter the outer alignment color for the QR Code.
COLUMN O: Enter the color of the gradient.
COLUMN P: Enter the color of the center text.
COLUMN Q: Enter the transparency of the background as true or false.
COLUMN R: Select the module shape from the available ones.
COLUMN S: Select the finder shape from the available ones.
COLUMN T: Select the finder eye shape from the available ones.
COLUMN U: Select the outer alignment shape from the available ones.
COLUMN V: Select the inner alignment shape from the available ones.
COLUMN W: Enter the text you want in the center.

For UPI Payments:

COLUMN A: Enter the VPA of the recipient.
COLUMN B: Enter the name of the merchant.
COLUMN C: Enter the amount to be transferred.
COLUMN D: Enter any additional notes.
COLUMN E: Enter the name of each individual QR Code in the batch.
COLUMN F: For dynamic QR Codes, enter true, and leave blank for a static QR Code.
COLUMN G: Enter the format of the QR Code.
COLUMN H: Specify the size of the QR Code.
COLUMN I: Choose the error correction level.
COLUMN J: Select the style of Gradient, or leave blank if you do not wish to apply gradient.
COLUMN K: Enter the background color for the QR Code.
COLUMN L: Enter the foreground color for the QR Code.
COLUMN M: Enter the finder color for the QR Code.
COLUMN N: Enter the finder eye color for the QR Code.
COLUMN O: Enter the inner alignment color for the QR Code.
COLUMN P: Enter the outer alignment color for the QR Code.
COLUMN Q: Enter the color of the gradient.
COLUMN R: Enter the color of the center text.
COLUMN S: Enter the transparency of the background as true or false.
COLUMN T: Select the module shape from the available ones.
COLUMN U: Select the finder shape from the available ones.
COLUMN V: Select the finder eye shape from the available ones.
COLUMN W: Select the outer alignment shape from the available ones.
COLUMN X: Select the inner alignment shape from the available ones.
COLUMN Y: Enter the text you want in the center.

Note: The default currency for UPI Payments is INR.

For Venmo:

COLUMN A: Enter the email or phone number of the recipient.
COLUMN B: Enter the amount.
COLUMN C: Enter any additional notes.

COLUMN D: Enter the name of each individual QR Code in the batch.
COLUMN E: For dynamic QR Codes, enter true, and leave blank for a static QR Code.
COLUMN F: Enter the format of the QR Code.
COLUMN G: Specify the size of the QR Code.
COLUMN H: Choose the error correction level.
COLUMN I: Select the style of Gradient, or leave blank if you do not wish to apply gradient.
COLUMN J: Enter the background color for the QR Code.
COLUMN K: Enter the foreground color for the QR Code.
COLUMN L: Enter the finder color for the QR Code.
COLUMN M: Enter the finder eye color for the QR Code.
COLUMN N: Enter the inner alignment color for the QR Code.
COLUMN O: Enter the outer alignment color for the QR Code.
COLUMN P: Enter the color of the gradient.
COLUMN Q: Enter the color of the center text.
COLUMN R: Enter the transparency of the background as true or false
COLUMN S: Select the module shape from the available ones.
COLUMN T: Select the finder shape from the available ones.
COLUMN U: Select the finder eye shape from the available ones.
COLUMN V: Select the outer alignment shape from the available ones.
COLUMN W: Select the inner alignment shape from the available ones.
COLUMN X: Enter the text you want in the center.

For WhatsApp:

COLUMN A: Enter the calling country code.
COLUMN B: Enter the phone number
COLUMN C: Enter the text message.
COLUMN D: Enter the name of each individual QR Code in the batch.
COLUMN E: For dynamic QR Codes, enter true, and leave blank for a static QR Code.
COLUMN F: Enter the format of the QR Code.
COLUMN G: Specify the size of the QR Code.
COLUMN H: Choose the error correction level.
COLUMN I: Select the style of Gradient, or leave blank if you do not wish to apply gradient.
COLUMN J: Enter the background color for the QR Code.
COLUMN K: Enter the foreground color for the QR Code.
COLUMN L: Enter the finder color for the QR Code.
COLUMN M: Enter the finder eye color for the QR Code.
COLUMN N: Enter the inner alignment color for the QR Code.
COLUMN O: Enter the outer alignment color for the QR Code.
COLUMN P: Enter the color of the gradient.
COLUMN Q: Enter the color of the center text.
COLUMN R: Enter the transparency of the background as true or false
COLUMN S: Select the module shape from the available ones.
COLUMN T: Select the finder shape from the available ones.
COLUMN U: Select the finder eye shape from the available ones.

COLUMN V: Select the outer alignment shape from the available ones.
COLUMN W: Select the inner alignment shape from the available ones.
COLUMN X: Enter the text you want in the center.

For Wifi login:

COLUMN A: Enter the SSID of the Wifi.
COLUMN B: Set the visibility to True for it to be visible or leave blank for it to be hidden.
COLUMN C: Enter the network type from the available types of network.
COLUMN D: Set the password for the Wifi.
COLUMN E: Enter the name of each individual QR Code in the batch.
COLUMN F: For dynamic QR Codes, enter true, and leave blank for a static QR Code.
COLUMN G: Enter the format of the QR Code.
COLUMN H: Specify the size of the QR Code.
COLUMN I: Choose the error correction level.
COLUMN J: Select the style of Gradient, or leave blank if you do not wish to apply gradient.
COLUMN K: Enter the background color for the QR Code.
COLUMN L: Enter the foreground color for the QR Code.
COLUMN M: Enter the finder color for the QR Code.
COLUMN N: Enter the finder eye color for the QR Code.
COLUMN O: Enter the inner alignment color for the QR Code.
COLUMN P: Enter the outer alignment color for the QR Code.
COLUMN Q: Enter the color of the gradient.
COLUMN R: Enter the color of the center text.
COLUMN S: Enter the transparency of the background as true or false.
COLUMN T: Select the module shape from the available ones.
COLUMN U: Select the finder shape from the available ones.
COLUMN V: Select the finder eye shape from the available ones.
COLUMN W: Select the outer alignment shape from the available ones.
COLUMN X: Select the inner alignment shape from the available ones.
COLUMN Y: Enter the text you want in the center.

For YouTube:

COLUMN A: Enter the ID of the YouTube video you wish to link with QR Code.
(https://www.youtube.com/watch?v=VIDEO_ID)
COLUMN B: Enter the link of the YouTube video.
COLUMN C: Enter the device type.
COLUMN D: Enter the name of each individual QR Code in the batch.
COLUMN E: For dynamic QR Codes, enter true, and leave blank for a static QR Code.
COLUMN F: Enter the format of the QR Code.
COLUMN G: Specify the size of the QR Code.
COLUMN H: Choose the error correction level.
COLUMN I: Select the style of Gradient, or leave blank if you do not wish to apply gradient.
COLUMN J: Enter the background color for the QR Code.
COLUMN K: Enter the foreground color for the QR Code.

COLUMN L: Enter the finder color for the QR Code.
COLUMN M: Enter the finder eye color for the QR Code.
COLUMN N: Enter the inner alignment color for the QR Code.
COLUMN O: Enter the outer alignment color for the QR Code.
COLUMN P: Enter the color of the gradient.
COLUMN Q: Enter the color of the center text.
COLUMN R: Enter the transparency of the background as true or false
COLUMN S: Select the module shape from the available ones.
COLUMN T: Select the finder shape from the available ones.
COLUMN U: Select the finder eye shape from the available ones.
COLUMN V: Select the outer alignment shape from the available ones.
COLUMN W: Select the inner alignment shape from the available ones.
COLUMN X: Enter the text you want in the center.

For Zelle Pay:

COLUMN A: Enter the token number.
COLUMN B: Enter the amount.
COLUMN C: Enter any text memo.
COLUMN D: Enter the username of the recipient.
COLUMN E: Enter the name of each individual QR Code in the batch.
COLUMN F: For dynamic QR Codes, enter true, and leave blank for a static QR Code.
COLUMN G: Enter the format of the QR Code.
COLUMN H: Specify the size of the QR Code.
COLUMN I: Choose the error correction level.
COLUMN J: Select the style of Gradient, or leave blank if you do not wish to apply gradient.
COLUMN K: Enter the background color for the QR Code.
COLUMN L: Enter the foreground color for the QR Code.
COLUMN M: Enter the finder color for the QR Code.
COLUMN N: Enter the finder eye color for the QR Code.
COLUMN O: Enter the inner alignment color for the QR Code.
COLUMN P: Enter the outer alignment color for the QR Code.
COLUMN Q: Enter the color of the gradient.
COLUMN R: Enter the color of the center text.
COLUMN S: Enter the transparency of the background as true or false.
COLUMN T: Select the module shape from the available ones.
COLUMN U: Select the finder shape from the available ones.
COLUMN V: Select the finder eye shape from the available ones.
COLUMN W: Select the outer alignment shape from the available ones.
COLUMN X: Select the inner alignment shape from the available ones.
COLUMN Y: Enter the text you want in the center.

BULK UPDATE FOR EXISTING QR CODES

The Bulk Update feature lets you quickly change the web links or data inside many existing QR Codes at once.

Step 1: Get Your QR Codes Ready (Export)

- Go to "All QR Codes": Find this tab on the left of your QRStuff dashboard.
- Pick Your Codes: Use the checkboxes next to the Code ID to select all the QR Codes you want to change.
- Download Data: Click the Export Selected QR Codes button.
- Save File: An Excel file containing the data for your chosen codes will download to your computer.

The screenshot shows the QRStuff dashboard with the 'All QR Codes' tab selected. The dashboard has a purple sidebar with navigation links: Overview, QR Codes, Projects, All QR Codes, Batch History, Analytics, Integrations, Teams, Account, API Keys, and Logout. The main content area is titled 'All QR Codes' and includes a search bar, a 'Create QR Code' button, and a 'Sort by: Newest First' dropdown. Below this is a section for moving QR codes to a project, with a 'Move 4 QR Code to' dropdown and a 'Project' dropdown. There are buttons for 'Move Codes To Project', 'Export Selected QR Codes', and 'Bulk Update'. A table of QR codes is displayed with columns: Code ID, Created, Name, Contents, Short Url, Data Type, and Hits. The table contains 10 rows of data, with the first row highlighted. A 'Bulk Update' button is visible at the bottom right of the table.


Code ID	Created	Name	Contents	Short Url	Data Type	Hits
87342	2025-11-03	QR Code 87342	Text: plain text	https://s.qr.ly/be1g2uk	Plain Text	0
87338	2025-11-03	QR Code 87338	Text: plain text	https://s.qr.ly/6o1g2ug	Plain Text	0
87337	2025-11-03	QR Code 87337	URL: https://www.t...	https://s.qr.ly/mal1g2uf	Website URL	0
87255	2025-10-27	test	Text: kjkn	https://s.qr.ly/3bl1g2sd	Plain Text	0
87253	2025-10-27	QR Code 87253	URL: https://www.q...	https://s.qr.ly/k41g2sb	Website URL	0
87252	2025-10-27	QR Code 87252	URL: https://www.q...	https://s.qr.ly/o41g2sa	Website URL	1
87059	2025-10-17	QR Code 87059	URL: https://www.q...	https://s.qr.ly/ul1g2ne	Website URL	1
87058	2025-10-17	utm	URL: https://transp...	https://s.qr.ly/11g2nd	Website URL	1
87049	2025-10-16	QR Code 87049	Text: why	https://s.qr.ly/5k1g2nd	Plain Text	1

Step 2: Make Your Changes in the Excel File

- Open the File: Open the downloaded Excel file (it looks like a spreadsheet).
- Edit the Content: Look for the column labeled "Contents" and type in the new data for each QR Code.
- Important Rule: Do not change the Code ID number. This is how the system knows which QR Code to update. Make sure the new information matches the original Data Type.
- Save: Save and close the spreadsheet, keeping it in an Excel format.

Step 3: Upload and Start the Update

- Click "Bulk Update": Go back to the "All QR Codes" page and click the Bulk Update button.
- Upload the File: In the window that pops up, select the edited Excel file from your computer.
- Submit: Click Submit to start the update.
- Go to Monitoring: The system will automatically take you to the Batch History page to watch the process.



Step 4: Check Results and Fix Errors (Batch History)

- **Monitor Status:** On the Batch History page, your update job will be listed. You will see immediately if it was Completed or if it Failed with errors. The summary shows how many records were successfully Completed and how many resulted in Errors.
- **Download the Error Report:** If any updates failed, click the Export Report option. This downloads a clean file showing only the rows that failed and the exact reason for the error.
- **Fix and Re-Upload:** Use this error report to quickly fix the data in your original file, and then repeat Step 3 to process only the failed QR Codes.

The screenshot displays the QRstuff.com interface. On the left is a purple sidebar with navigation links: Overview, QR Codes, Batch History (selected), Analytics, Integrations, Teams, Account, API Keys, and Logout. The main content area has a top navigation bar with a back arrow and 'Batch History'. A green banner at the top reads 'Batch Processing Complete!' with a 'Completed' status. Below this, the batch name 'Batch-Update-5234' is shown with a status of 'Completed' and '2 of 2 records processed'. Three summary cards are displayed: 'totalRecords' with a value of '2', 'Completed' with a value of '2', and 'Processing Time' with a value of '2s'. A green message box states: 'Perfect execution! Your batch processing completed successfully with a 100% success rate. All records have been processed and are ready for use.' Below this is a 'Processing Summary' table:

Batch Name	Batch-Update-5234	Processing Time	2s
Total Records	2	Completed At	2025-11-06
Success Rate	100%	Status	Completed

At the bottom of the main content area is an 'Export Report' button. The bottom of the page shows a 'Google Chrome' browser indicator and a user profile icon.

MULTIPLE DATA TYPES IN SINGLE BATCH

The platform now supports processing several data types within one batch file. Select the required data types, and download a sample file to understand the supported structure and format.

PROCESSING LARGE BATCHES

The maximum online batch size limit of 500 codes per batch has been set to avoid undue server load across the sessions of other users. For registered users with more than 5,000 codes to

generate, we offer a service whereby the job is run locally at our end - the cost of this service is US\$2.50/100 codes.

Just send us the Excel file containing your batch data and we'll look after the rest. The QR code image files for the batch are then emailed to you in zip files.

Payment is either by Paypal or your Debit/Credit card prior to job commencement and turnaround is 48-72 hours from when payment has been received.

[Send us an email](#) for more information.